



## 1) Open the newly generated wsdl in XML spy



## 2) Got to text view and highlight from the tag </wsdl:message>



3) Insert the following text.

```
<wsdl:portType name="Z_SR015_2b">
    <wsdl:operation name="MIIS_SR015">
        <wsdl:input message="p1:p2.ValidateMeterReading"/>
        <wsdl:output message="p1:p2.ValidateMeterReading"/>
    </wsdl:operation>
</wsdl:portType>
<wsdl:binding name="Z_SR015_2bBinding" type="p1:Z_SR015_2b"
xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
    <soap:binding style="document"
transport="http://schemas.xmlsoap.org/soap/http"
xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/">
        <wsdl:operation name="MIIS_SR015">
            <soap:operation soapAction="http://sap.com/xi/WebService/soap1.1"
xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/">
                <wsdl:input>
                    <soap:body use="literal"
xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/">
                </wsdl:input>
                <wsdl:output>
                    <soap:body use="literal"
xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/">
                </wsdl:output>
            </wsdl:operation>
        </wsdl:binding>
<wsdl:service name="Z_SR015_2bService">
    <wsdl:port name="MIIS_SR015Port" binding="p1:Z_SR015_2bBinding"
xmlns:wsdl="http://schemas.xmlsoap.org/wsdl/">
        <soap:address
location="http://esssapas1.essot.local:8051/sap/bc/srt/xip/sap/Z_SR015_2b?sap-client=231"
xmlns:soap="http://schemas.xmlsoap.org/wsdl/soap/">
    </wsdl:port>
</wsdl:service>
</wsdl:definitions>
```


4) Your wsdl should now look like the below

```


<wsdl:portType name="Z_SR015_2b">
    <wsdl:operation name="p1_Z_SR015_2b">
        <wsdl:input message="p1_Z_SR015_2b"/>
        <wsdl:output message="p1_Z_SR015_2b"/>
    </wsdl:operation>
    <wsdl:operation name="p2_Z_SR015_2b">
        <wsdl:input message="p2_Z_SR015_2b"/>
        <wsdl:output message="p2_Z_SR015_2b"/>
    </wsdl:operation>
</wsdl:portType>
<wsdl:binding name="Z_SR015_2bBinding" type="p1_Z_SR015_2b">
    <wsdl:operation name="p1_Z_SR015_2b">
        <wsdl:input message="p1_Z_SR015_2b"/>
        <wsdl:output message="p1_Z_SR015_2b" style="document" transport="http://schemas.xmlsoap.org/soap/http" xmlns:soap="http://schemas.xmlsoap.org/soap/http" xmlns:wsdl="http://schemas.xmlsoap.org/wsdl"/>
    </wsdl:operation>
    <wsdl:operation name="p2_Z_SR015_2b">
        <wsdl:input message="p2_Z_SR015_2b"/>
        <wsdl:output message="p2_Z_SR015_2b" style="document" transport="http://schemas.xmlsoap.org/soap/http" xmlns:soap="http://schemas.xmlsoap.org/soap/http" xmlns:wsdl="http://schemas.xmlsoap.org/wsdl"/>
    </wsdl:operation>
</wsdl:binding>
<wsdl:port name="MIS_SR015Port" binding="Z_SR015_2bBinding" xmlns:wsdl="http://schemas.xmlsoap.org/wsdl">
    <wsdl:address location="http://essencp1.essent.local:8051/sap/bc/rt/xip/sap/Z_SR015_2b?sap-client=231" xmlns:soap="http://schemas.xmlsoap.org/soap/http" xmlns:wsdl="http://schemas.xmlsoap.org/wsdl"/>
</wsdl:port>
</wsdl:definitions>

```

5) Go to the “schema/WSDL” view and alter all references for Z\_SR015\_2b to Z\_SR015\_2c



6) it should look like the below.



7) Save.